VEST OR PULL-ON GARMENT

Materials: 8 oz. of Jaeger "Classic" Superfine Scotch Fingering, 3 -ply (7d. per oz.),1 pair of No. 10 Jaeger knitting needles, and a medium crochet hook.

Measurements: Length from shoulder, 26 inches; width all round under the arms, 36 inches; length of sleeve seam, 9 inches. Tension: 7 stitches to 1 inch in width, and 10 rows to 1 inch in depth. Abbreviations: K. = knit; p. = purl; sts. = stitches; st.-st. stocking-stick; inc.

p. = purl; sts. = stitches; st.-st. stocking-stick; inc. = increase or increasing; dec. = decrease or decreasing; d.c. = double crochet.

Casting on: If you cast on with two needles work into the back of all caston sts. to produce firm edges, but if you use the thumb method this is not necessary.

THE BACK

Begin at the lower edge. Cast on 126 sts. and work 3 inches in k.1, p.1 rib. Change to st.-st. and continue until the work measures 18 inches from the beginning, finishing after a p. row.

The Armhole Shaping: Dec.1 st. at both ends of every row until 114 sts. remain. Continue without dec. until the armholes measure 6 inches on the straight, finishing after a p. row.

The Neck Shaping:
Next row - K. 39, cast off 36, k. to end. Continue on the last 39 sts., dec. 1 st. at the neck edge on every alternate row until 34 sts. remain. Continue without dec. until the armhole measures 8 inches on the straight. Cast off. Join the wool to the inside edge of the other side and work up this to match the first.

THE FRONT

Work this exactly like the back.

THE SLEEVES

Begin at the lower edge. Cast on 84 sts. and work 3 inches in k.1, p.1 rib. Change to st.-st., inc. 1 st, at both ends of the 5th row, then on every alternate row until there are 124 sts. on the needle Continue without inc. until the work measures 8.5 inches from the beginning, measured down the centre. Now shape the top by dec. 1 st. at both ends of every row until 114 sts. .remain. Cast off.

THE MAKING UP

Press the work on the wrong side with a warm iron and damp cloth. Join the shoulders, sew in the sleeves and press the seams. Sew up the side and sleeve seams and press them. Work 1 row of d.c. round the neck edge.